



## Application Note

# Generic Data Import Parser setup



1) All Licenses are entered in LAM under the Licenses Tab, Add New Line Item.

License Asset Manager

Release Version : 8.0.0.0

Logbut

Expirations PO Licenses Usage Vendors Tools Servers Reports Settings Daemon

Add\_New\_Line\_Item Import Configure\_View Filter

Total Quantity: 1104 Total Amount: \$1,514,733.00

Check All Uncheck All Delete

Tool	PO	Quantity	Tool Type	Site	Restrict	Purchase Type	Expiry Date	Amount	Actions
0-In	1234567	4	FLEXLM		LAN- San Diego	Subscription	Dec-31-2016	\$60,000.00	Edit
0-In	312887	2	DSLS		LAN- India	Subscription	Dec-31-2013	\$30,000.00	Edit
3D Design Viewer		1					Aug-14-2014	\$0.00	Edit
3D Design Viewer	432143241	2	FLEXLM		LAN- Wichita	Subscription	Mar-31-2017	\$25,000.00	Edit
A1		10	NORMAL		LAN- San Diego	Subscription	Sep-24-2016	\$0.00	Edit
A1		5					Nov-03-2018	\$0.00	Edit
Abaqus/CAE	2141441	2	FlexLM		LAN- San Diego	Subscription	Aug-14-2017	\$45,500.00	Edit
Abaqus/Standard	2141441	5	DSLS		WAN-ETZ	Perpetual_W/_Maintenance	May-17-2018	\$47,000.00	Edit
Abaqus Bundle	12345	1	FlexLM	Pune	WAN-US	Subscription	Apr-15-2016	\$42,000.00	Edit
accurev		6	Reprise	MHT	LAN- Wichita	Subscription	Feb-17-2017	\$0.00	Edit
Acrobat 2		10	TEMP		LAB 101	Maintenance	Dec-31-2016	\$0.00	Edit
Acrobat 2	415500021	80	Borrowable		NODE	Perpetual_W/O_Maintenance	Apr-01-2016	\$22,500.00	Edit
Adams		100	NORMAL		WAN	Subscription	May-29-2011	\$125,000.00	Edit
Allegro Design Editor	134520	4	FlexLM		LAN- Chelmsford	Subscription	Apr-07-2016	\$42,250.00	Edit
Allegro Design Editor XL	134520	5				Subscription	Mar-18-2012	\$33,100.00	Edit
Allegro PCB Libraries	134520	4			LAN- India	Subscription	Jul-07-2016	\$12,000.00	Edit
Allegro PCB Router	134520	2	NORMAL		WAN-US	Subscription	Jul-07-2016	\$32,500.00	Edit
Arbortext		1					Jun-25-2015	\$0.00	Edit
AutoDesk Bundle		1	FlexLM			Perpetual_W/_Maintenance	Dec-01-2016	\$0.00	Edit

2) To add a Line Item you must enter a Vendor, Tool, Quantity, License Type, and linking method.

License Asset Manager

Update Line Item

Vendor\*: Tanner

Tool/Line Item \*: GenericTool

Date Acquired\*: Oct 12 2017

Expiry Date\*: Oct 12 2018

Quantity\*: 100

Version:

PO#: 5223894 Add New PO

Tool Type:

Purchase Type: Subscription

Capital \$: 0.0

Expense \$: 0.0

Installer: Admin Admin

Responsible Person: Admin Admin

License No:

Notes:

Standalone

MakeModel: Add New MakeModel

OS: Add New OS

Standalone Type:

HostOrUser:

HardwareKey:

Networked

Restriction:

License Type: Generic

Log File:

Select / Add:  Daemon  Port@Host  License File

Daemon/ISV: GenericDaemon@192.168.1.106 Add New Daemon

Submit Cancel

3) To add Generic data please select a Licenses Type as "Generic".

When adding a Generic license, use the standard Add New Line Item in the

© 2018 TeamEDA. All rights reserved. TeamEDA, the TeamEDA logo, License Asset Manager and all marks relating to TeamEDA products and services referenced herein are either trademarks or registered trademarks of TeamEDA or its affiliates. All other trademarks are the property of their respective owners.

Licenses Tab. Put in what information you want, then go the "Networked" section (lower right) and under License Type, select Generic:

4) Select Daemon. To add Daemon please enter daemon name, server (or Add New Server), and Port. Select new Daemon and Finally click submit button.

The screenshot displays the 'LICENSE ASSET MANAGER' interface. At the top, there is a header 'LICENSE ASSET MANAGER' and a sub-header 'Update Line Item'. Below this, there are dropdown menus for 'Vendor\*' (Tanner), 'Tool/Line Item \*' (GenericTool), and 'DateAcquired:\*' (Oct 12, 2017). A browser window titled 'Add Daemon - Google Chrome' is overlaid on the main interface, showing the 'Add Daemon' form. This form has the following fields: 'Daemon/ISV\*' (text input), 'Vendor\*' (Tanner), 'Server:\*' (192.168.1.106), 'Server2' (text input), 'Server3' (text input), 'Tag\*' (text input), and 'Daemon Notes' (text area). To the right of the 'Server:\*' field is a 'Port' label and a text input field. Below the 'Server:\*' field are three 'Add' buttons. At the bottom of the browser window, there is a 'Select / Add:' section with radio buttons for 'Daemon', 'Port@Host', and 'License File'. The 'Daemon' option is selected, and the 'Add New Daemon' button is circled in red. Below the browser window, the main interface shows 'Standalone Type:', 'HostOrUser:', 'HardwareKey:', 'Log File:', and 'Test' button. The 'License Type:' is set to 'Generic'.

5) This Line Item will now show up in LAM under Licenses Tab, but it is not yet pushed over to the UM side.

6) Click Usage, and click Monitor Update on the Usage/Home page.

7) Now you should see the Tool/Tag Name, Daemon in the Usage/Home Monitor list, but the Status will be red. Now we are ready to import data using GenericdataImport template.

8) Click Usage->Parsers->Generic Data Import. Select Generic Data Import.

9) Download excel template. Insert and save data in it.

10) Select Tag Name from dropdown list for generic data import. Choose template file with a data to import and click Import button.

LICENSE ASSET MANAGER

[Logout](#)  
 Release Version : 8.0.0.0  
[Logout](#)

Expirations PO Licenses **Usage** Vendors Tools Servers Reports Settings Daemon
Home Current History Denials Users Groups Batch Alerts

### Licenses being monitored

[Monitor Update](#)

● Scheduler : UP

Tool Name	Tag Name	Daemon Name	Type	Status	Info	History	User Details	Group Details	Heatmap
accurev	accurev_demo	unknown	RLM	UNK	Realtime	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
AltiumTool	Altium	N/A	Altium	NO LOG	N/A	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
GenericTool1	generic1Tag	unknown	Generic	OK	N/A	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
GenericTool	GenericTag	unknown	Generic	OK	N/A	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
generic test	generic_test	unknown	Generic	OK	N/A	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
MATLAB	matlab_demo	MLM	FlexLM	OK	Realtime	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
MATLAB	matlab_demo2	MLM	FlexLM	OK	Realtime	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>
MATLAB	matlab_demo3	MLM	FlexLM	OK	Realtime	<a href="#">Graphs</a>	<a href="#">Table</a>	<a href="#">Table</a>	<a href="#">Graph</a>

Parsers
Admin

- Altium Parsing Setup
- DSLS Denial Parsing Setup
- FLEX Comprehensive Checkout Parsing Setup
- FLEX Denial Parsing Setup
- FlexNet Manager Parser
- Generic Data Import
- Sentinel Parsing Setup
- Windchill Parsing Setup

LICENSE ASSET MANAGER

[Logout](#)  
 Release Version : 8.0.0.0  
[Logout](#)

Expirations PO Licenses **Usage** Vendors Tools Servers Reports Settings Daemon
Home Current History Denials Users Groups Batch Alerts

### Generic Data Import

Import your file

Select Tag Name

Choose .xls file for Import

Choose File

No file chosen

Import

This Generic Data Import is a special tool which allows you to import your old data into LAMUM. The import utility will only work with given excel template.

Note : Please download this excel template file and use it to import your data.

testdemtag

accurev\_demo

Altium

generic\_test

GenericTag

generic1Tag

matlab\_demo

matlab\_demo2

matlab\_demo3

microsemi2

TestMicrosemi

NX\_demo

NX-demo2

TESTVENDOR\_tag

TestTag1



PTC

It may take some time depending on the number of records to be imported and the files in them, which are to be uploaded.

© 2018 TeamEDA. All rights reserved. TeamEDA, the TeamEDA logo, License Asset Manager and all marks relating to TeamEDA products and services referenced herein are either trademarks or registered trademarks of TeamEDA or it's affiliates. All other trademarks are the property of their respective owners.

TeamEDA | 1001 Elm Street, Suite 305 | Manchester | NH | 03101 | [www.teameda.com](http://www.teameda.com) | (+1)603.656.5200

11) Generic Data Import template has two sheets license and users.



12) License worksheet

- Datetime
- Feature
- License Available
- License Used

## 13) Users worksheet:

- Feature
- Datetime
- Checkout Duration
- Username
- Checkout
- Client/Machine Name

## 14) Error Messages and Warning Messages :

- Date Format : Date format accepting while inserting dates are -  
 mm/dd/yyyy hh:mm:ss  
 mm/dd/yy hh:mm:ss  
 yy/mm/dd hh:mm:ss  
 yyyy/mm/dd hh:mm:ss  
 yyyy-mm-dd hh:mm:ss

## Generic Data Import

### Import your file

Select Tag Name	Choose .xls file for Import	Action
<input type="text"/>	<input type="button" value="Choose File"/> No file chosen	<input type="button" value="Import"/>

This Generic Data Import is a special tool which allows you to import your old data into LAMUM  
 The import utility will only work with given excel template.

**Note :** Please download this [excel template file](#) and use it to import your data.

Importing records may take some time depending on the number of records to be imported and the files in them, which are to be uploaded.

Error while inserting DATETIME in LICENSE SHEET cell A2  
 Error while inserting DATETIME in LICENSE SHEET cell A4  
 Error : LICENSE USED ONLY CONTAIN NUMBERS - LICENSE SHEET cell D4  
 Error : LICENSE AVAILABLE ONLY CONTAIN NUMBERS - LICENSE SHEET cell C60

Total Number of Rows Successfully inserted : 0

[LOGO](#)  
 Release Version : 8.0.0.0  
[Logout](#)

## LICENSE ASSET MANAGER

Expirations	PO	Licenses	Usage	Vendors	Tools	Servers	Reports	Settings	Daemon
Home	Current	History	Denials	Users	Groups	Batch	Alerts	Parsers	Admin

### Generic Data Import

Import your file

Select Tag Name	Choose .xls file for Import	Action
<input type="text"/>	<input type="button" value="Choose File"/> <span style="margin-left: 10px;">No file chosen</span>	<input type="button" value="Import"/>

This Generic Data Import is a special tool which allows you to import your old data into LAMUM  
 The import utility will only work with given excel template.

Note : Please download this [excel template file](#) and use it to import your data.

Importing records may take some time depending on the number of records to be imported and the files in them, which are to be uploaded.

Import Data Successfully Done.

- After you brose to the Import Generic data and click Import, it will read in the data and provide you error message if dataformat is invalid.
- It will Insert a data and show you message **Import Data Successfully done.**

13) Now you can see the Tool/Tag Name, Daemon in the Usage/Home Monitor list with status green.

Contact TeamEDA for questions:  
 603-656-5200  
[support@teameda.com](mailto:support@teameda.com)